

Nextcloud AIO installatie op proxmox

Stap 1: container

Maak een Debian container

Stap 2 : Docker + Docker compose

Stap 3: Nexctcloud AIO docker compose

```
---
version: "3.8"

volumes:
  nextcloud_aio_mastercontainer:
    name: nextcloud_aio_mastercontainer # This line is not allowed to be changed

services:
  nextcloud:
    image: nextcloud/all-in-one:latest
    restart: always
    container_name: nextcloud-aio-mastercontainer # This line is not allowed to be changed
    volumes:
      - nextcloud_aio_mastercontainer:/mnt/docker-aio-config # This line is not allowed to be
changed
      - /var/run/docker.sock:/var/run/docker.sock:ro # May be changed on macOS, Windows or
docker rootless. See the applicable documentation. If adjusting, don't forget to also set
```

```
'DOCKER_SOCKET_PATH'!
```

```
ports:
```

```
- 8080:8080
```

```
- 8443:8443 # Can be removed when running behind a web server or reverse proxy (like Apache, Nginx and else). See https://github.com/nextcloud/all-in-one/blob/main/reverse-proxy.md
```

```
environment: # Is needed when using any of the options below
```

```
- APACHE_PORT=11000 # Is needed when running behind a web server or reverse proxy (like Apache, Nginx and else). See https://github.com/nextcloud/all-in-one/blob/main/reverse-proxy.md
```

```
- APACHE_IP_BINDING=192.168.0.10 # Should be set when running behind a web server or reverse proxy (like Apache, Nginx and else) that is running on the same host. See https://github.com/nextcloud/all-in-one/blob/main/reverse-proxy.md
```

```
# - COLLABORA_SECCOMP_DISABLED=false # Setting this to true allows to disable Collabora's Seccomp feature. See https://github.com/nextcloud/all-in-one#how-to-disable-collaboras-seccomp-feature
```

```
# - DOCKER_SOCKET_PATH=/run/user/1000/docker.sock # Needs to be specified if the docker socket on the host is not located in the default '/var/run/docker.sock'. Otherwise mastercontainer updates will fail. For macos it needs to be '/var/run/docker.sock'
```

```
# - DISABLE_BACKUP_SECTION=false # Setting this to true allows to hide the backup section in the AIO interface.
```

```
- NEXTCLOUD_DATADIR=/data/ # Allows to set the host directory for Nextcloud's datadir. See https://github.com/nextcloud/all-in-one#how-to-change-the-default-location-of-nextclouds-datadir
```

```
# - NEXTCLOUD_MOUNT=/mnt/ # Allows the Nextcloud container to access the chosen directory on the host. See https://github.com/nextcloud/all-in-one#how-to-allow-the-nextcloud-container-to-access-directories-on-the-host
```

```
- NEXTCLOUD_UPLOAD_LIMIT=15G # Can be adjusted if you need more. See https://github.com/nextcloud/all-in-one#how-to-adjust-the-upload-limit-for-nextcloud
```

```
# - NEXTCLOUD_MAX_TIME=3600 # Can be adjusted if you need more. See https://github.com/nextcloud/all-in-one#how-to-adjust-the-max-execution-time-for-nextcloud
```

```
- NEXTCLOUD_MEMORY_LIMIT=2048M # Can be adjusted if you need more. See https://github.com/nextcloud/all-in-one#how-to-adjust-the-php-memory-limit-for-nextcloud
```

```
# - NEXTCLOUD_TRUSTED_CACERTS_DIR=/path/to/my/cacerts # CA certificates in this directory will be trusted by the OS of the nexcloud container (Useful e.g. for LDAPS) See https://github.com/nextcloud/all-in-one#how-to-trust-user-defiend-certification-authorities-ca
```

```
# - NEXTCLOUD_STARTUP_APPS=deck twofactor_totp tasks calendar contacts # Allows to modify the Nextcloud apps that are installed on starting AIO the first time. See https://github.com/nextcloud/all-in-one#how-to-change-the-nextcloud-apps-that-are-installed-on-the-first-startup
```

```
# - NEXTCLOUD_ADDITIONAL_APKS=imagemagick # This allows to add additional packages to the Nextcloud container permanently. Default is imagemagick but can be overwritten by modifying this value. See https://github.com/nextcloud/all-in-one#how-to-add-os-packages-permanently-to-the-nextcloud-container
```

```
# - NEXTCLOUD_ADDITIONAL_PHP_EXTENSIONS=imagick # This allows to add additional php extensions to the Nextcloud container permanently. Default is imagick but can be overwritten by modifying this value. See https://github.com/nextcloud/all-in-one#how-to-add-php-extensions-permanently-to-the-nextcloud-container
```

```
# - NEXTCLOUD_ENABLE_DRI_DEVICE=true # This allows to enable the /dev/dri device in the Nextcloud container which is needed for hardware-transcoding. See https://github.com/nextcloud/all-in-one#how-to-enable-hardware-transcoding-for-nextcloud
```

```
# - TALK_PORT=3478 # This allows to adjust the port that the talk container is using.
```

Created 2026-04-29 08:53:31 UTC by Admin

Updated 2026-04-29 09:00:09 UTC by Admin